NETHASP LICENSE MANAGER 8.31 INSTALLATION ON WINDOWS OPERATING SYSTEM (SERVER & XP)

1. Check IP Address on the server and note the same. Recommended IP Address to be 192.168.0.1 and subnet mask – 255.255.255.0

2. Check IP Address on workstation machines and ensure that they are in the same subnet as Server. Recommended IP Addresses would be as 192.168.0.x (Except 1 which is given to server) and subnet mask – 255.255.255.0

3. Copy NHSRV.INI file to C:\WINDOWS\SYSTEM32 or C:\WINNT\SYSTEM32 folder

4. Open NHSRV.INI and change the Server IP Address

   NHS_IP_LIMIT – should have IP Address range

   As per our recommended IP Address setting value should be

   192.168.0.*

   NHS_ADAPTER_IP – should be the server ip address and its subnet mask

   As per our recommended IP Address setting value should be

   192.168.0.1-255.255.255.0

5. If this is not a first time installation / single user is already exists then Uninstall all HASP Drivers / Software on the machine first by checking the Add / Remove Program list. Also ensure that no other machine on the network has NETHASP License Manager Software Installed.

6. Attach the Hasp key to the server machine preferably on the back side of the computer.

7. Install the Nethasp License Manager Software Ver 8.31 – LMSETUP.EXE file

HASP
HL
Aladdin
Do you want to install HASP License Manager as an application or as a service?
Application (nhsrvw32.exe)
Service (nhsrvice.exe)
< Back
Next >
Cancel

HASP
HL
Aladdin
Setup will install HASP License Manager in the following folder.
To install into a different folder, click Browse and select another folder.
You can choose not to install HASP License Manager by clicking Cancel to exit Setup.
Destination Folder
C:\Program Files\Aladdin\HASP LM
Browse...
< Back
Next >
Cancel

HASP
HL
Aladdin
Enter the name of the Program Manager group to add HASP License Manager icons to:
HASP License Manager
Accessories
Administrative Tools
ApexDC++
Codec Pack
Crystal Reports 9 Tools
CutePDF
DC++
DivX
Free Download Manager
Games
Google Earth
Google Video
HASP Emulator PE V2.33
HP
< Back
Next >
Cancel

HASP
HL
Aladdin
HASP License Manager needs a HASP HL Device Driver version which is not currently installed on this system.
HASP HL Driver Version: 5.19
This driver will be installed now.
Next >
Cancel

HASP
HL
Aladdin
HASP HL Drivers successfully installed.
Next >

HASP
HL
Aladdin
HASP License Manager has been successfully installed.
Do you want to start it now ?
NOTE: HASP key must be attached to the system in order to start the HASP License Manager.
Yes
No
Finish
Cancel

8. Copy Nethasp.ini file to application folder path.

9. Configure Nethasp.ini file

NH_SERVER_ADDR – should have the Server IP Address

As per our recommended IP Address setting value should be

192.168.0.1

10. Copy HaspASC.Hsp / Fields.dbf (DOS ASCFA) file to Application Folder

11. Start the Application and test the same.